

# 1 bytemark

bytemark — command-line client for managing services with Bytemark

## Synopsis

**bytemark** [**global options**] *command* [**command options**] [**command arguments**]

## DESCRIPTION

**bytemark** is a command-line client you can use to interact with Bytemark services (<https://www.bytemark.co.uk/>).

You can use this software to signup for a new Bytemark account, or to use an existing account. You can perform a variety of tasks, such as create a Cloud Server, manage an existing Cloud Server, or connect to a Cloud Server via serial console. Get started straight away by running **bytemark help**.

If you're a programmer, you might also want to integrate with our API (<https://www.bytemark.co.uk/docs/api/>).

## GLOBAL OPTIONS

Global options apply to any subsequent command.

### **--help**

Show usage instructions, including a list of available commands.

### **--help *command***

Show instructions on how to use a specific command.

### **--version**

Show the version of this software.

### **--yubikey**

Use this option if you have a Bytemark-provided Yubikey that you use for authentication. You'll be prompted for the one-time password.

### **--yubikey-otp *string***

Use this option if you want enter the Yubikey one-time password on the command-line rather than be prompted for it.

### **--session-validity *num***

Specifies the length of time, in seconds, that your login session will be valid for without running another command.

### **--2fa-otp *string***

Use this option if you want enter the 2 Factor Authentication one-time password on the command-line rather than be prompted for it.

### **--debug-level *num***

Set the verbosity of debugging information (for troubleshooting purposes).

### **--user *username***

Specify the username to use for the subsequent command. This is the same username you would use to login to the Bytemark Panel (<https://panel.bytemark.co.uk/>).

### **--account *account\_name***

Specify the account to use for the subsequent command. Most people have a single account with the same name as their username, so don't need to use this option. However, some people manage Cloud Servers on multiple accounts.

### **--endpoint *URL*, --api-endpoint *URL*, --auth-endpoint *URL*, --billing-endpoint *URL*, --spp-endpoint *URL***

The default endpoints shouldn't need to be changed, but if for some reason you need the client to communicate with different endpoints then you can use these options.

**--config-dir *dir***

The client stores its configuration in `$HOME/.bytemark` by default. You can specify a different directory with this option.

**--output-format *format***

The format to return any data in. This mostly affects the *show* commands. Available formats: *human*: the default - outputs data in a human-readable bulleted-list kind of way *json*: output data in JSON format *table*: output data as a table. By default this will output all the fields for each object. Set the *--table-fields* flag to *help* on a command that supports table output to see the list of fields available.

## COMMANDS

There are a variety of commands that let you easily manage your services with Bytemark. Get started by running **bytemark help**.

**help**

Show usage instructions, including a list of available commands.

**help command**

Show instructions on how to use a specific command.

## EXAMPLES

**bytemark help create**

Show instructions on how to use the *create* command.

**bytemark help create server**

Show instructions on how to use the *create server* command.

**bytemark create server --authorized-keys-file *~/ssh/id\_rsa.pub* *stoneboat.http***

Creates a new Cloud Server called *stoneboat* in the *http* group. The specified public key will be installed to the root user so that you can use it to login.

**bytemark show server *stoneboat.http***

Show information about the Cloud Server *stoneboat* in the *http* group.

**bytemark shutdown *stoneboat.http***

Shutdown the Cloud Server *stoneboat* in the *http* group.

## FILES

***~/.bytemark***

Configuration is stored in this directory by default.

***~/.bytemark/debug.log***

This log holds debugging information. If you encounter a problem with this software, we might ask you to provide a copy of this file.

***~/.bytemark/token***

This is where the time-limited authentication token is stored.

## BUGS

Please send an email to [<support@bytemark.co.uk>](mailto:support@bytemark.co.uk) if you encounter any problems and we'll be more than happy to assist.

## AUTHORS

This software and associated documentation is developed and maintained by Bytemark, primarily by Telyn Z. Roat.